



SYSTEM REQUIREMENTS


To run *The Incredible Machine 2* on your computer, you need at least 5 1/2 MB of hard drive space and 2 MB of RAM. Of that 2MB, you must have 560K (573,440 bytes) free conventional memory and 256K (262,144 bytes) of free expanded memory (EMS).

NOTE FOR CD-ROM USERS

Installing *The Incredible Machine 2* takes 1 1/2 MB or 5 1/2 MB of hard drive space, depending if you select Partial Install or Full Install, .

EASY START FOR DOS USERS

All kinds of things are competing for your computer's memory. Various drivers are needed to run stuff like your mouse, joystick, sound card, CD-ROM drive, and anything else you have hitched up to your machine. So it's easy to fall short of the memory you need to run *The Incredible Machine 2* with its high-resolution animations, music and sound effects, and hundreds of parts. That's where the Easy Start disk comes in handy. It will let you run your game with the greatest efficiency and speed possible. Just follow the steps on the back of this card to install and run the game.



006491100



MS DOS & CD-ROM INSTALLATION

These instructions assume that you are using floppy drive A:, hard drive C:, and/or CD-ROM drive D:. If not, please substitute as appropriate.

1. After booting your machine, insert *The Incredible Machine 2* disk # 1 into drive A: or the CD into the CD-ROM drive. Then, depending on which drive you're using, type the letter of the drive containing the disk (A: or D:) [ENTER].
2. Type **INSTALL** [ENTER].
3. Follow the install instructions as they appear on your screen. At the main install menu, choose "Make an Easy Start Disk" once you are satisfied with the audio configuration.
4. Place the enclosed Easy Start disk in the drive when the install program asks for it. The install program will adjust your Easy Start disk specifically to your computer's needs.
5. Choose "Accept these choices" to copy the necessary files to your hard drive.



6. To play *The Incredible Machine 2*, either turn on your computer with the Easy-Start disk in the floppy drive, or if your machine is running, put the Easy Start disk in the floppy drive and press **CTRL+ALT+DEL**. *The Incredible Machine 2* will automatically start.

CONVENTIONAL START

If you have the proper memory configuration, you may play *The Incredible Machine 2* by typing the following:

C: [ENTER]

CD \SIERRA\TIM2 [ENTER]

TIM2 [ENTER]